

# IN PROGRESS

## Changed files

- clients.conf
- proxy.conf
- sites-available/govroam
- sites-available/govroam-inner-tunnel
- mods-available/govroam\_logs

Delete any other links in the sites-enabled directory ('status' can be left/added if you're allowing status checks). Attempting to run 'govroam' and 'default' will likely result in problems stating the RADIUS server.

### clients.conf:

```
# Configure a Network Access Server (e.g. wireless controller) to accept
traffic from.

client NAS {
    secret = something
    ipaddr = 10.10.20.1
}

# Configure the JISC NRPS as a client as it will be sending request from
your people abroad.

client roaming0 {
    secret = something
    ipaddr = 192.168.0.1
    operator = "NRPS"
}

# Configure your local IdP as a client. (Omit for Visited Only ORPS)
client localidp1 {
    secret = something
    ipaddr = 10.10.10.31
    operator = "localidp1"
}
```

### proxy.conf:

```
# Blackhole (REJECT) where the realm is missing.

realm NULL {
```

```
}

# Realms that don't match any other listed send to the pool of govroam
servers
realm "~^[^@.]( [a-zA-Z0-9-]+\.)+[a-zA-Z]{2,6}$" {
    auth_pool = govroam
    nostrip
}

# Pool of govroam servers
home_server_pool govroam {
    home_server = roaming0
    type = client-port-balance
}

#Govroam server configuration
home_server roaming0 {
    ipaddr = roaming0.govroam.uk
    port = 1812
    type = auth
    secret = something
    status_check = status-server # Checks status of govroam server
    operator = "NRPS"
}

# Handle requests for the realm 'localnet'. (Omit for Visited Only ORPS)
realm localnet {
    nostrip
    auth_pool = ad_auth
}

server_pool ad_auth {
    type = client-port-balance
    home_server = localidp1
}

home_server localidp1 {
    status_check = status-server
    ipaddr = 10.10.10.31
    secret = something
    port = 1812
    type = auth
    operator = "localidp1"
}

}
```

**sites-available/govroam:**

```
server govroam {
    # Listen on the default port on all IP addresses
    listen {
        type = auth
        ipaddr = *
    }

    authorize {
        preprocess
        update request {
            Operator-Name = 1your.domain # Adds the Operator
Name attribute to the request, if it doesn't already exist.
        }
        auth_log
        suffix # Identifies the realm
        files
        cui
        mschap # used for plain/non-eap ntlm_auth testing
        eap {
            ok = return
        }
    }

    authenticate {
        ntlm_auth
        Auth-Type MS-CHAP {
            mschap
        }
        eap
    }

    preacct {
        preprocess
        suffix
    }

    accounting {
        detail
    }

    post-auth {
        # Lots of logging
        reply_log
        # Only send F-TICKS to Jisc when proxying between sites.
        if ( "%{home_server:operator}" != "NRPS" && "%{client:operator}" !=
"NRPS") {
            f_ticks
        }
    }
}
```

```
}
    govroam_log
    cui
    Post-Auth-Type REJECT {
        attr_filter.access_reject
        reply_log
    }
}

pre-proxy {
    pre_proxy_log
    cui
    if("%{Packet-Type}" != "Accounting-Request") {
        attr_filter.pre-proxy
    }
}

post-proxy {
    post_proxy_log
    attr_filter.post-proxy
}
}
```

And then create a symlink from sites-enabled/govroam to sites-available/govroam.

### **sites-available/govroam-inner-tunnel**

```
server inner-tunnel {

    authorize {
        preprocess
        auth_log
        suffix
        update control {
            Proxy-To-Realm := LOCAL
        }
        eap {
            ok = return
        }
        files
    }
    pap
    mschap
}
authenticate {
    ntlm_auth
    files
    Auth-Type PAP {
        pap
    }
}
```

```

        }
        Auth-Type MS-CHAP {
            mschap
        }
    }
    eap
}

post-auth {
    cui
    reply_log
    govroam_log
    f_ticks
    Post-Auth-Type REJECT {
        reply_log
        govroam_log
        f_ticks
    }
}
}

```

And then create a symlink from sites-enabled/govroam-inner-tunnel to sites-available/govroam-inner-tunnel.

### mods-available->govroam\_logs:

```

# F-TICKS
linelog f_ticks {
    filename = syslog
    format = ""
    reference = "f_ticks.%%{reply:Packet-Type}: -format}"
    f_ticks {
        Access-Accept ="F-
TICKS/govroam/1.0#REALM=%{Realm}#VISICOUNTRY=GB#VISINST=%{Operator-
Name}#CSI=%{Calling-Station-Id}#RESULT=OK#FEDID=XX#" # Replace XX with your
supplied ID

    }

linelog govroam_log {
    filename = syslog
    format = ""
    reference = "govroam_log.%%{reply:Packet-Type}: -format}"
    govroam_log {
        Access-Accept = "govroam-auth#ORG=%{request:Realm}#USER=%{User-
Name}#CSI=%{Calling-Station-Id}:-Unknown Caller Id}#NAS=%{Called-
Station-Id}:-Unknown Access Point}#CUI=%{reply:Chargeable-User-Identity}:-
Unknown}#MSG=%{EAP-Message}:-No EAP Message}#RESULT=OK#"
        Access-Reject = "govroam-auth#ORG=%{request:Realm}#USER=%{User-
Name}#CSI=%{Calling-Station-Id}:-Unknown Caller Id}#NAS=%{Called-

```

```
Station-Id}:-Unknown Access Point}#CUI=%{%{reply:Chargeable-User-Identity}:-Unknown}#MSG=%{%{reply:Reply-Message}:-No Failure Reason}#RESULT=FAIL#"
    }
}
```

And then create a symlink from mods-enabled/govroam\_logs to mods-available/govroam\_logs.

Use the **details.log** file in mods-available to configure how the local logs are formatted and stored. The format below stores the logs by date and time making it easier to use logrotate or similar to archive off older logs.

```
detail auth_log {
    detailfile = ${radacctdir}/%Y%m%d/request-detail-%H:00
    header = "%{Packet-Src-IP-Address} - %t"
    detailperm = 0600
    suppress {
        User-Password
    }
}

detail reply_log {
    detailfile = ${radacctdir}/%Y%m%d/reply-detail-%H:00
    header = "%{Packet-Src-IP-Address} - %t"
    detailperm = 0600
}

detail pre_proxy_log {
    detailfile = ${radacctdir}/%Y%m%d/pre-proxy-detail-%H:00
    header = "%{Packet-Src-IP-Address} - %t"
    log_packet_header = yes
    detailperm = 0600
    suppress {
        User-Password
    }
}

detail post_proxy_log {
    detailfile = ${radacctdir}/%Y%m%d/post-proxy-detail-%H:00
    header = "%{Packet-Src-IP-Address} - %t"
    detailperm = 0600
}
```

Once configured you can test using [eapol\\_test](#)

From:  
<https://wiki.govroam.uk/dokuwiki/> - **Govroam**

Permanent link:  
[https://wiki.govroam.uk/dokuwiki/doku.php?id=siteadmin:basic\\_freeradius\\_orps\\_and\\_idp\\_configuration&rev=1669991224](https://wiki.govroam.uk/dokuwiki/doku.php?id=siteadmin:basic_freeradius_orps_and_idp_configuration&rev=1669991224)

Last update: **2022/12/02 14:27**

