

## Changed files

- clients.conf
- proxy.conf
- sites-available → govroam
- mods-available → govroam\_logs

Delete any other links in the sites-enabled directory ('status' can be left/added if you're allowing status checks). Attempting to run 'govroam' and 'default' will likely result in problems stating the RADIUS server.

### clients.conf:

```
# Configure a Network Access Server (e.g. wireless controller) to accept traffic from.
```

```
client NAS {
    secret = something
    ipaddr = 10.10.20.1
}
```

```
# Configure the JISC NRPS as a client as it will be sending request from your people abroad.
```

```
client roaming0 {
    secret = something
    ipaddr = 192.168.0.1
    operator = "NRPS"
}
```

```
# Configure your local IdP as a client. (Omit for Visited Only ORPS)
```

```
client localidp1 {
    secret = something
    ipaddr = 10.10.10.31
    operator = "localidp1."
}
```

### proxy.conf:

```
# Blackhole (REJECT) where the realm is missing.
```

```
realm NULL {
}
```

```
# Realms that don't match any other listed send to the pool of govroam servers
```

```
realm "~.+ $" {
```

```
    auth_pool = govroam
    nostrip
}

# Pool of govroam servers
home_server_pool govroam {
    home_server = roaming0
    type = client-port-balance
}

#Govroam server configuration
home_server roaming0 {
    ipaddr = roaming0.govroam.uk
    port = 1812
    type = auth
    secret = something
    status_check = status-server # Checks status of govroam server
    operator = "NRPS"
}

# Handle requests for the realm 'localnet'. (Omit for Visited Only ORPS)
realm localnet {
    nostrip
    auth_pool = ad_auth
}

server_pool ad_auth {
    type = client-port-balance
    home_server = localidp1
}

home_server localidp1 {
    status_check = status-server
    ipaddr = 10.10.10.31
    secret = something
    port = 1812
    type = auth
    operator = "localidp1"
}
```

### **sites-available->govroam:**

```
server govroam {
    # Listen on the default port on all IP addresses
    listen {
        type = auth
    }
}
```

```
    ipaddr = *
}

authorize {
    preprocess
    update request {
        Operator-Name := 1your.domain # Adds the Operator
Name attribute to the request.
    }
    auth_log
    suffix # Identifies the realm
    files

}

authenticate {
}

preacct {
    preprocess
    suffix
}

accounting {
    detail
}

post-auth {
    # Lots of logging
    reply_log
    if ( "%{home_server:operator}" != "NRPS" && "%{client:operator}" !=
"NRPS") {
        f_ticks
    }
    govroam_log
    Post-Auth-Type REJECT {
        attr_filter.access_reject
        reply_log
    }
}

pre-proxy {
    pre_proxy_log
    if("%{Packet-Type}" != "Accounting-Request") {
        attr_filter.pre-proxy
    }
}

post-proxy {
    post_proxy_log
    attr_filter.post-proxy
}
```

```
}  
}
```

And then create a symlink from sites-enabled/govroam to sites-available/govroam.

### mods-available->govroam\_logs:

```
# F-TICKS  
linelog f_ticks {  
    filename = syslog  
    format = ""  
    reference = "f_ticks.%%{reply:Packet-Type}: -format}"  
f_ticks {  
    Access-Accept ="F-  
TICKS/govroam/1.0#REALM=%{Realm}#VISICOUNTRY=GB#VISINST=%{Operator-  
Name}#CSI=%{Calling-Station-Id}#RESULT=OK#FEDID=XX#" # Replace XX with your  
supplied ID  
}  
  
linelog govroam_log {  
    filename = syslog  
    format = ""  
    reference = "govroam_log.%%{reply:Packet-Type}: -format}"  
govroam_log {  
    Access-Accept = "govroam-auth#ORG=%{request:Realm}#USER=%{User-  
Name}#CSI=%{Calling-Station-Id}:-Unknown Caller Id}#NAS=%{Called-  
Station-Id}:-Unknown Access Point}#CUI=%{reply:Chargeable-User-Identity}:-  
Unknown}#MSG=%{EAP-Message}:-No EAP Message}#RESULT=OK#"  
    Access-Reject = "govroam-auth#ORG=%{request:Realm}#USER=%{User-  
Name}#CSI=%{Calling-Station-Id}:-Unknown Caller Id}#NAS=%{Called-  
Station-Id}:-Unknown Access Point}#CUI=%{reply:Chargeable-User-Identity}:-  
Unknown}#MSG=%{reply:Reply-Message}:-No Failure Reason}#RESULT=FAIL#"  
    }  
}
```

And then create a symlink from mods-enabled/govroam\_logs to mods-available/govroam\_logs.

Use the **details.log** file in mods-available to configure how the local logs are formatted and stored. The format below stores the logs by date and time making it easier to use logrotate or similar to archive off older logs.

```
detail auth_log {  
    detailfile = ${radacctdir}/%Y%m%d/request-detail-%H:00  
    header = "%{Packet-Src-IP-Address} - %t"  
    detailperm = 0600
```

```
        suppress {
            User-Password
        }
    }

detail reply_log {
    detailfile = ${radacctdir}/%Y%m%d/reply-detail-%H:00
    header = "%{Packet-Src-IP-Address} - %t"
    detailperm = 0600
}

detail pre_proxy_log {
    detailfile = ${radacctdir}/%Y%m%d/pre-proxy-detail-%H:00
    header = "%{Packet-Src-IP-Address} - %t"
    log_packet_header = yes
    detailperm = 0600
    suppress {
        User-Password
    }
}

detail post_proxy_log {
    detailfile = ${radacctdir}/%Y%m%d/post-proxy-detail-%H:00
    header = "%{Packet-Src-IP-Address} - %t"
    detailperm = 0600
}
```

From:  
<https://wiki.govroam.uk/dokuwiki/> - Govroam

Permanent link:  
[https://wiki.govroam.uk/dokuwiki/doku.php?id=siteadmin:basic\\_freeradius\\_orps\\_configuration&rev=1662385099](https://wiki.govroam.uk/dokuwiki/doku.php?id=siteadmin:basic_freeradius_orps_configuration&rev=1662385099)

Last update: **2022/09/05 13:38**

